

# ONBOARDING

## GETTING STARTED

### How to Run Your Bounce Rental Solutions Website On Your Own Domain

#### Step 1

If you will be capturing credit card information on your checkout page, you will need an SSL installed on your site. Contact us to get that process started.

#### Step 2

In your Bounce Rental Solutions dashboard, click on **"Hi, Your Name" > "My Profile"**. Click the **"Edit Profile"** button. Check the **"Run Website On Domain"** box. Change the Company Subdomain to your domain.

In the instance below, the website is [www.upstateinflatable rentals.com](http://www.upstateinflatable rentals.com) so from the drop-down list, the **".com"** extension was selected and **"upstateinflatable rentals.com"** was filled out in the **"company subdomain"** box. Check the **"Use SSL On Domain"** box, assuming your SSL has been installed. If not, leave it unchecked for now.


The screenshot shows the Bounce Rental Solutions dashboard. At the top, there is a navigation bar with the logo on the left and links for MY WEBSITE, MY ACCOUNT, and HELP on the right. Below the navigation bar is a teal menu bar with links: Home, Customers, Rental Products, Orders, Reports, Billings, Email Templates, Website, and Rental Form. The main content area is titled 'EDIT PROFILE' and contains a form with the following fields:

First Name Michael	Last Name Stratford	Company Name traces trampolines
Run Website On Domain <input checked="" type="checkbox"/> com	Company Subdomain upstateinflatable rentals	Use SSL On Domain <input checked="" type="checkbox"/>

## Step 3

Login to your account with the company (GoDaddy.com, etc.) with whom your domain name is registered. Go to your DNS setting and click the [DNS Zone File](#) tab. Click the edit button and change the A (Host) IP address to [3.233.97.62](#). (The screenshots below is from a GoDaddy account and may look different if your domain is registered with another company.)






Locate your domain name in your hosting account and click the [DNS](#) button.



Your DNS Records should look somewhat similar to the image below. Change the A (host) IP address to [3.233.97.62](#).

### Records

Last updated 7/20/2021 9:54 PM

Type	Name	Value	TTL	
A	@	3.233.97.62	600 seconds	
CNAME	upstateinfla...	@	1 Hour	
CNAME	www	@	10800 seco...	
CNAME	_263d9916...	_eb04ad697f8bb655d75a...	1 Hour	
CNAME	_domainco...	_domainconnect.gd.doma...	1 Hour	
NS	@	ns19.domaincontrol.com	1 Hour	
NS	@	ns20.domaincontrol.com	1 Hour	
SOA	@	Primary nameserver: ns19...	1 Hour	

[ADD](#)

Shortly after making these changes, when you type in your domain name your site that was running on a Bounce Rental Solutions sub domain will now be running on your domain. In our experience this can take anywhere from a couple of minutes to 24 hours.